

OnScreenKeys User guide



Leírás

A OnScreenKeys szoftver egy kisegítő technológia azon emberek számára, akik fogyatékoságukból adódóan nem tudják a hagyományos billentyűzetet, vagy egeret használni.

A OnScreenKeys képernyőbillentyűn minden megtalálható, ami a hagyományos billentyűzeten, és még sok egyéb, ami a számítógépe használatát könnyebbé teszi.

Normális billentyű lenyomása helyett a felhasználó az egérrel a képernyőbillentyűn gépel, melynek segítségével könnyedén írhat bármilyen képernyőn lévő szövegmezőbe.

OnScreenKeys egy beépített egér klikkmentési funkciót kínál, melynek segítségével akkor is tud egérklikkmentést végezni, ha az egér gombját már nem képes megnyomni.

Many more integrated features will make working on the computer easier.

The software includes an integrated voice output, which can be used to send written text to the computer loudspeaker. Integration of additional voices from other companies like AT&T, Acapela is possible.



Telepítés

Installation from CD

If OnScreenKeys was delivered on a CD, put it in your computer's CD-ROM drive. The installation will start automatically.

If installation does not start automatically:

If installation from CD does not start automatically, OnScreenKeysSetup.exe on the CD must be started manually.

First start

OnScreenKeys automatically detects which language you have specified as the standard language in Windows® and configures this software automatically accordingly. You may change the language for the keyboard among many other settings by accessing the configuration menu, which you can enter by using the settings button of the keyboard:



Gépelés

Szövegszerkesztő ablak

You need to open a text window that you can type into. For demonstration purposes a text window is opened automatically when the software is being started.

Any executable file can be set up to be started automatically when OnScreenKeys is being started.


You may type into any text editor of your choice, for example, Microsoft Word®, or eMail software.

Please remember that (just like when typing with a normal computer keyboard) the cursor must be blinking inside the window.




How to click keys and buttons

To trigger keys on the keyboard automatically without pressing down the mouse buttons manually, the auto-click function ("Hover") must be activated. The time before a key is triggered automatically can be freely adjusted.



Autoclick pause button



Head mouse users may profit from the autoclick-pause function. If this option has been selected, the auto-click-pause button will be visible on the keyboard. If you want to change your position in a chair or just turn the head, the mouse cursor will move over the computer screen due to the body movement, and it may trigger keys on the keyboard undesirably. By clicking the "Auto-click pause button" once, you may deactivate the keyboard's Auto-click function until this button is triggered again.

N	Nagyon	Nincs	Nő	Nap
Nem	Neki	Na	Nagy	Ne

Szótár

As soon as you have typed the first letter of a new word, word predictions will be shown. If the desired word is shown, you may just select it to type this word.

OnScreenKeys provides a triple word prediction. This means that the software will try to foresee the next upcoming word. As soon as you see the desired word, you may select it.

Upper/ lower case

Maybe you will notice that OnScreenKeys is trying to set the correct upper or lower case state for the keyboard automatically. You can trigger the shift button to change the shift state manually.



Shift key

Note that words which are selected by selecting one of the word prediction buttons will be typed just the way they are displayed on the screen. You can set the the shift state with the shift button before you select a word.

If you want to change the case of the last typed word you may select the following button:



Word shift key



Correction

There are 3 delete functions in the software:



Delete last character

Use this button to delete the last character.



Delete last word

Ez a gomb törli a legutóbbi szót

Other keys



Tab key



Word shift key



Shift key



Escape key



Caps Lock billentyű (Permanent upper case typing)



Windows



Quick text-macro key



Delete word from user word book: If you once typed a word incorrectly and did not correct it, it will appear in the word prediction again. To delete this word, select this button, and then trigger a click on the button that shows the incorrect word.



CD tray: Opens or closes the CD tray.



Autoclick pause button: Ennek a gombnak a segítségével deaktiválni tudja az autoclick szolgáltatását a billentyűzetnek. Ezután csak ezzel a gombal tudja újra aktiválni.



Általános beállítások



Kis méretűve tesz



Kilépés



Hang: Activate/ deactivate speech output function

Extra-, AltGr- and Ctrl-Key



Extended keys

By clicking the extra key on the virtual keyboard you can access all special functions that exist on a normal keyboard.



AltGr-key

The AltGr key is used to write special characters.



CTRL billentyű

The Ctrl key is used to do so-called "short cuts".

The effect of a short cut depends on the application it is used within.

Adapting the keyboard

Többsnyelvűség

People who speak multiple languages will profit from the "language switch function" which allows changing both the language for word prediction and the keyboard layout quickly. By default, the software will use the language that is also used in Windows®.

To change the language temporarily, trigger the following key: 

Select the desired language from one of the empty selection boxes, then click "Activate".

If you want to switch the language of the keyboard again, you have to use the "language switch button" again, then click on the "Activate" button besides the desired language.



Nyelv (Általános beállítások)

To change the language that will be used for user menus and dialogs, select the desired language in the configuration menu.


[Standard language for word prediction and menus](#)

English (USA) ▼

Language for menus and dialogs in this software. This language will also be as the primary language for word prediction.

Billentyű mérete


The size of the keyboard can be changed in the configuration menu.



The blue rectangle shows the size in relation to your computer screen.

User-defined keys

There are 4 keys on the keyboard which can be filled with any contents in the configuration menu.



Beszéd kimenet

Please note that this function will only be available after the trial period of the software if it is part of the license that you have purchased.

Ez a gomb aktiválja, vagy deaktiválja a hangos felolvasási szolgáltatást.

Depending on the current status, the following symbols are shown.



Speech output is deactivated.



Speech output is activated.



Speech output is deactivated due to an error.

If the speech output function is activated, every typed line will be sent to the speech engine when the enter key is triggered.



Triggering the enter key again without any new words written will repeat the last spoken sentence. This may come handy if you were not understood correctly.

Speak every single word

If the option "Speak single words" is activated, each word will be sent to the speech output function immediately after typing it.

If this option has not been activated, the last typed line will be sent to the speech output when the enter key is triggered.

To select a voice for speech output, you may go the configuration menu and change the voice that is assigned to a specific language.

Please note that you will have to trigger the "Save voice" button which can be found right below the voice selection field after you have changed a language-voice combination.

If you are using the software for more than one language, you may select a different voice for each language.

If you change the keyboard language by triggering the language switch key, the voice you have assigned to this language will be selected automatically for speech output.



Egér gomb tálcá



Please note that this function will only be available after the trial period of the software if it is part of the license that you have purchased.

If you have difficulties pressing the buttons of a real mouse you should use these virtual mouse buttons.

Using the virtual mouse buttons may be a bit unfamiliar at first, so here is a short explanation. First of all you should consider which button you would use on a normal mouse to do what you want to do.

For example, to open a text file you would need to do a double left click.

Select the desired mouse click, then move the mouse pointer to the location where this mouse click shall be executed.

Egér gomb funkció



Dupla klikk



Bal klikk



Jobb klikk



'Fogd és vidd' kattintás



Repeated drag-/ drop clicks
(for games like e. g. Spider Solitaire)



Deactivates and minimizes the mouse button bar.



Maximizes the mouse button bar.

2 values may be important in order to work comfortably with the mouse click function:



1) **Nyomva tartás ideje**

Dwell time means the time span before a mouse click is done at the mouse pointer's current position.




2) **Mozgatási hibatűrés**

If you have problems keeping the mouse pointer still then you should raise the tremor tolerance.

Egér gombsor mérete

The size of the mouse button bar can be changed in the configuration menu.




The blue rectangle shows the size in relation to your computer screen.

Compensation for spasticities

Please note that this function will only be available after the trial period of the software if it is part of the license that you have purchased.

Make real computer mouse ignore clicks.



This option causes the mouse to ignore clicks.

Mouse clicks on e. g. the desktop can only be triggered by the mouse click bar.

This option can compensate for spasticities in hand which may lead to unwanted dragging of files into e. g. the recycle bin.

When this option has been activated, the Escape key on the computer keyboard can be used to deactivate or to resume the ignoring of mouse clicks of the computer mouse.

Szöveg makrók

Quick text-macro key



By triggering the 'quick text-macro key', the titles of the quick text macros will be displayed in the keyboard.

When you trigger one of these titles, the pre-assigned contents of this text macro will be typed.

Title and contents of text macros can be assigned or created in the configuration menu.

You may for example create a text macro with the title 'Farewell' and assign 'Good-bye!' as its contents.

Szöveg makrók

Since 10 quick text-macros may be a little too few for a trained user, it is possible to add further text macros which can be triggered by certain key combinations.

These text macros can be requested by typing "#" on the keyboard.

One possible way of giving text macros names is to use abbreviations.

Grouping is a good way of keeping your text macros clearly arranged.

For example all text macros which are related to food, should start with 'Food:' in their name.

This way you can create names which can be easily recognized, like 'Food:Salad', 'Food:Bread', etc.



Szószedet

OnScreenKeys provides a comprehensive dictionary by default.


The software learns new words and sentences as you type them and adopts to your writing style. Anyway, it might be a good decision in some cases to import own documents to make the software adapt to your writing style immediately.

Use the vocabulary import function in the configuration menu to import your text documents.

Extrák

Automatikus indítás

OnScreenKeys can be configured so that it starts automatically when Windows® is started.



Color scheme

The color scheme of the software can be changed to compensate for visual impairment.

Colors


Standard colors

Black/ White


Foreground color

Background color

Auto-click color



Preview



Hang

Sound output for triggering keys can be activated or deactivated.

Sound

Play sound when keys are triggered



Troubleshooting

Kérdéseikkel, valamint további információért kérjük küldjön egy levelet a info@onscreenkeys.com címre.